

FreeTAK Server User Manual



FTS V. 2.1
Oct 2023
Release

1. Introduction

Welcome to the user manual for the FreeTAKServer (FTS) Web User interface (webUI)!

FreeTAKServer, as of Release 2.2, provides Situational Awareness and other capabilities such as:

- Web administration
- Federation Service (Connecting two or more FTS instances)
- Data Package upload and retrieval
- Private data package (user to user)
- Image transfer and storage
- COT recording in a database
- Execution of common task list (using the ExCheck plugin for WinTAK; ATAK plugin only available to users with tak.gov access)
- SSL Encryption
- User Management
- REST API for creation of information such as emergency, Enemy units and so on

About the Web UI


FTS webUI allows administrators to easily manage the server.

This video, based on a pre-production version, provides an overview of most features described in the manual

https://www.youtube.com/watch?v=q4BpolzIDLw&ab_channel=%2aDA-B6%2a

WebUI is a completely separate application connecting to the FTS backend.

It uses an API to seamless query server functions. Depending on his deployment, may or may not be seen from remote machines.



Installation and configuration

This section provides an overview of the installation process. Refer to the online documentation for details.

To install FTS and the UI type in a console

```
sudo python3 -m pip install FreeTAKServer[ui]
```

Setup your Configuration

your administrator will need to configure the following files

- Config.py for the UI
- MainConfig.py for FTS

Start FTS

```
nohup sudo python3 -m FreeTAKServer.controllers.services.FTS
```

Start the WebUI


```
nohup sudo python3  
/usr/local/lib/python3.8/dist-packages/FreeTAKServer-UI/run.py
```

Basics

Login

Open a browser and navigate to [webUIIP]:[PORT]

For example 127.0.0.1:5000



Insert the user and password created with the function “System User” (see 4.1).
Click login

The function “Don't have an account? **Create**” could be useful to provide anyone with the link to the UI with the ability to create a System user. For security purposes it's disabled in the standard configuration and his activation should be avoided


First login can be done using:

- Username: admin (all non capital)
- Password: password (all non capital)

It's strongly suggested to immediately create a new user and delete the generated one.

1.0 Navigation


To the Left of the main screen, there is a menu with 6 sub menus. These are: Home, Mission, User, Connect, Configure and About.



Each of these is linked to a different screen with specific information to be seen and edited. The current section is highlighted with a blue dot

- **Home:** System status
- **WebMap:** a web client displaying all is sent to your FTS server
- **Mission:** Data Packages and other files
- **User:** UI users and groups configuration
- **Connect:** send CoTs and system messages
- **Configure:** Services and federated servers
- **About:** FTS and web UI version and special thanks

1.1 Top Navigation Bar



The Events button is currently inactive. It provides a list of the last 5 events. The user button allow to log out or to edit the current user Profile

1.2 Profile Screen

The screenshot shows the 'EDIT PROFILE' screen. It contains the following fields and a button:

- [EDIT PROFILE]**: A blue link at the top left.
- Name (disabled)**: A text input field containing 'Eliopoli HQ'.
- Group**: A text input field containing 'Pirates'.
- Token**: A text input field containing '...'.
- Password**: A text input field containing '...'.
- Certs**: A text input field containing 'Eliopoli HQ.zip'.
- Save**: A blue button at the bottom left.

Use this screen to change the current login user password, token and group

2.0 Home


Here the main information about FTS can be visualized. This information is periodically updated from the server. You can change this period in the UI configuration

([UIInstallation]/**UI/app/**__init__.py

. Default, expressed in milliseconds are

- USER INTERVAL= '180000'
- SERVER HEALTH INTERVAL = '180000'
- SYS STATUS INTERVAL = '600000'


2.1 System Status



The status of FTS services is visualized as a series (6) of rotating concentric circles. The information is color coded:

- **Blue**: Service is running and activated
- **Red**: Service is activated but not running (screenshot)
- **Gray**: Service is turned off (See 5.1 System Configuration)

2.2 Run Time & connected clients



This section shows the start and current run time of the FTS, as well as the number of connected clients. The start time is provided by the server, so if you are in a different time zone you may see negative up times.

2.3 System Health



In this section the % resources required by the server are displayed as its consumption of CPU, RAM, and Disk. The gauge shows both numerical (RAM: 32) as well as visual (circle $\sim\frac{1}{3}$ full) values.

2.4 Logs


The figure shows a 'Logs' table with a dark background. In the top right corner, the word '[LOGS]' is displayed in blue. The table has four columns: 'TIME', 'TYPE', 'FILE', and 'MESSAGE'. The first row of data shows a warning message at 20:01 from FederationClientService.py:151, stating 'exception thrown creating new federation [Erno III] Connection refused'.

TIME	TYPE	FILE	MESSAGE
20:01	WARNING	FederationClientService.py:151	exception thrown creating new federation [Erno III] Connection refused

Last Errors and other log messages will appear here

3.0 WebMap

Since FTS 1.8, the UI has a Tab to a webMap. The webmap is a separate component, part of the FreeTAKHub concept (see <https://github.com/FreeTAKTeam/FreeTAKHub> for more details)




The webmap is a partial TAK client only. It displays all the connected clients and the COT sent from the moment in which it connects. Clicking on another tab closes the webmap, no memory of past events is kept.

3.1 Webmap Special functions


Following functions are also available:

- Zoom in and out


- Measure distances and bearing



- Import KML
 - Drag and drop a valid KML into the map to display it (server only, not shared with clients)



- Add markers to the map (right click) and send to all the connected clients




A screenshot of a web application showing a map with a grid. A white dialog box is open over the map, containing the following fields and controls:


- Attitude:** A dropdown menu with 'Friend' selected.
- Type:** A dropdown menu with 'Rifleman' selected.
- Timeout:** A text input field containing '600', followed by a small 'S' icon.
- Name:** An empty text input field.
- Send:** A button at the bottom left of the dialog.
- Close:** A small 'X' icon at the top right of the dialog.

- *Attitude: the attitude of the target toward the users, reflected in the color*
- *Type: Basic infantry types are supported*
- *Timeout: time before the markers disappears in seconds*
- *Name: unique name of the marker, if the same name is re-used, it will move an existing marker*


- Delete an existing Marker



- Search COT by name




- Search geo location



- Select different map styles




- Filter COTs by type (each COT type is placed in a layer)



4.0 Mission

A multipurpose section with a broad role in managing data and files

4.1 Data Packages



Name	Author	Index	Is Private	Size (KB)	Submitted
NOAA_RNC.xml	KabulAfghanistan	214	☐	0.999	Tue, 12 Jan 2021 15:08:39 GMT
MOBAC-Maps-master.zip		215	☒	4.279	Tue, 12 Jan 2021 15:08:39 GMT
DAB6.zip	server	216	☒	7.462	Tue, 12 Jan 2021 15:08:39 GMT
ESRI Clarity.xml	KabulAfghanistan	219	☐	0.881	Tue, 12 Jan 2021 15:08:39 GMT
Google_Mapsources.zip	314C	220	☒	1.452	Tue, 12 Jan 2021 15:08:39 GMT
ESRI Clarity.xml	KabulAfghanistan	221	☐	0.882	Tue, 12 Jan 2021 15:08:39 GMT
MOBAC-Maps-master.zip	server	222	☐	4.44	Tue, 12 Jan 2021 15:08:39 GMT

DELETE ADD ...

From here one can see, add, download, delete and hide available data packages.

- **Add:** By pressing on the three dots in the bottom right of the menu, a dialogue will appear with your file explorer. Select the Zip file meant for upload and click on “open”. The dialogue will close. Now click on “add” (next to “delete” at the bottom left) and the file will be uploaded as a data package.

The default maximum size for a Data Package is 15 MB. You can change this size in the UI configuration ([UIInstallation]/**UI/app/**__init__.py

- **Download to local drive:** Simply click on the data package name in blue. The file will be downloaded to your “downloads” folder
- **Delete:** This can be done by selecting the undesired data packages (click anywhere except the blue name), the delete button will change to indicate the # of selected rows. Click “delete” (bottom left)
- **Index:** the unique index number of the Data Package in the DB
- **Hide:** The fourth information column from the right is labeled as “is private”. This function allows you to hide data packages from ATAK / WinTAK users simply by checking the box in this column. All private data packages, exchanged between clients, are listed as private
- **QR code:** opens a special image that contains the URL of the DP package. Useful to share certifications (see System Users). *Notice, the QR code will appears in a new windows, check out your Adblock or similar tools to ensure that the message is not blocked*

4.2 Mission / Data Sync



Name	Description	Keywords	Creator	Groups	Created
WintakMis	None	[]		[]	2023-11-26T21:23:10.916772Z
mi2	2nd part	[]		[]	2023-11-27T21:58:45.639903Z

[MISSION]

DELETE ADD

The Data Sync / Mission API in FTS enables clients like ATAK or WinTAK to share and track information collection as part of missions.

- **Mission Creation and Availability:** Once a client creates a mission, it's immediately accessible to others with the Plugin
- **Content Types:** Missions can include CoT (Cursor on Target) tracks, enterprise sync resources, and mission logs. CoT tracks are managed via UUIDs for real-time event updates. Mission Logs allow free-form text entries, viewable individually or as a complete log.
- **File Management:** Through the Enterprise Sync API, various file types (like GRGs, images, KML files) can be uploaded and associated with missions. Files are referenced by hashes based on their binary content, allowing search by time intervals and geographic locations.
- **Client Interactions with Missions:** The API supports adding/removing mission content, tracking changes made by other clients, and requesting updates. This ensures clients have a consistent view of mission contents.
- **Mission Logs:** Besides tracks and files, missions can include "Mission Logs" or "Recce Logs," comprising individual log entries posted by clients. Changes like updates, deletions, or additions to log entries, tracks, and files are tracked by TAK Server, creating a detailed change log.
- **Mission Subscription and Updates:** Clients can subscribe to missions, receiving CoT messages for each change, and request change logs for specific time ranges.
- **REST API:** Missions and related information are accessible via the FTS [REST API](#), modeling mission information as a resource hierarchy (e.g., 'mission' containing 'content'). Operations are based on standard HTTP verbs (GET, POST, PUT, DELETE) corresponding to CRUD operations, encoded as JSON objects. The API adheres to HTTP 1.1 standards and best practices for safety and idempotency, ensuring reliability in operations like mission creation, even with multiple concurrent requests.


This framework effectively streamlines mission coordination, offering robust, real-time data management and communication for clients.

In version 2.1 alfa, the buttons are not functional

4.3 ExCheck

ExCheck allows users to collaborate on the execution and monitoring of tasks based on templates. To use ExCheck, you need to have a server that supports it. FTS supports the plugin since version 1.3. See this article for an example of how to use it:

https://www.reddit.com/r/ATAK/comments/jzltvt/use_freetakserver_and_excheck_plugin_to/



Allows you to see, add and delete ExCheck templates.

- **Add:** Add: By pressing on the three dots in the bottom right of the menu, a dialogue of your file explorer will appear. Select the file meant for upload and click on “open”. The dialogue will close. Now click on “add” (next to “delete” at the bottom left) and the file will be uploaded as a data package.
The uploaded template must be valid in a XML format.
- **Delete:** This can be done by selecting the undesired data packages, and then clicking on “delete” (bottom left)

4.4 Federation

The federation function allows FTS to connect to another server of the TAK family and exchange information such as COT and chats. The current implementation (1.9) does not allow sending Data packages and Missions yet.

4.4.1 Federating to a legacy TAK server

To set up a federated connection with another server you need to upload the certificate authority to the target server.

Under the certs directory there's a file called `pubserver.pem` containing your server public certificate.

Download this file, rename it to something easy to remember like `FTS204.134.0.60.pem` and upload it to the Legacy TAK server you want to federate to.

4.4.2 Federating to a FTS server

- **On the federated server:** activate the Federation service under Configure/system configuration
- **On the federated client:** Simply create the connection to the federated server

[OUTGOING FEDERATIONS]					
Name	Address	Port	Fallback	Status	Rec. Interval
lantern	3.96.240.142	9000	None	Enabled	32
				DELETE	ADD

Here one can see the status of federated servers the current instance connects to, as well as deleting, editing and adding news ones.

- **Add:** Pressing the “Add” button will open an extension of the window. In the correct slots, fill out the pertinent information (Name, IP Address, and Port). Additionally, you can add a fallback (backup) server, by enabling or disabling the option. In the current version (1.5 this is not yet active) Press submit once finished.

In the event the status remains disabled it is likely there was an error in the creation of your federation, the associated error message can be found in the farthest right most column of your federation (you may need to scroll to the right to see it).

[OUTGOING FEDERATIONS]					
Name	Address	Port	Fallback	Status	Rec. Interval
lantern	3.96.240.142	9000	None	Enabled	32
				DELETE	ADD

Name	IP Address	Port
Fallback Server	lantern ▼	Status Enabled ▼
Max Retries	Rec Interval	

Submit

- **Editing:** When selecting the desired server, a new button labeled “editing” will appear next to “delete” (bottom right of panel). Pressing this will enter the information of the selected server in the otherwise blank fields. Information can now be edited to desired values.

- **Delete:** This can be done by selecting the undesired federation and then clicking on “delete” (bottom right)

5.0 User

Allows the user to add or delete System Users and edit user group permissions.

5.1 System users

This panel shows all of the registered users of the UI and allows the user to add and delete users. A System User, other than an anonymous one is associated with a group, a Token for API, a password that can be used to login into the ui and finally certificates allowing to securely connect to FTS

[SYSTEM USERS]					
Name	Group	Token	Password	Certs	Device Type
admin	1	*****	*****		mobile
					DELETE ADD

- **Add:** This can be done by clicking on the “add” button (bottom right of panel). An extension will appear, with empty fields for the new user’s name, group, token and password.
 - **Name:** name of the created user. For the certs deployment to work must be the same as a connected user (see below)
 - **Group:** group of individuals this user belong to (team a, team b, team c)
 - **Token:** gives an unique combination that this user can leverage for the FTS REST API. NOTICE: the field token is for any alphanumeric string. the prefix 'bearer' is NOT part of the token. The name “*Bearer authentication*” can be understood as “give access to the bearer of this token.”
 - **Password:** unique password that can be used for interact with the FTS
 - **Certs:** true/false. If true certs will be generated (see below)
- When creating an user In the UI, you will find a new flag. By selecting "mobile" you will generate an push a certificate that should work with:
- ATAK
 - iTAK
 - TAK Tracker

in alternative selecting desktop will generate and push a certificate for WinTAK

Once the fields have been filled, simply press submit to add a new user.

FreeTAKTeamSupport	123	123	123
Certs	True	Device Type	WinTAK
			Submit

- **Delete:** This can be done by selecting the undesired user and then clicking on “delete” (bottom right). You can only delete one user each time. **Since version 1.9 when you delete an user that has a certificate, the certificate will be invalid.**

5.1.1 Automate certificates creation and deployment

TAK clients can connect to a server using TCP or secure connection (SSL), this requires the creation of valid certification on the server that needs to be deployed to each client.

FTS supports an advanced system to generate and distribute valid certification.

When creating a system user, by leaving “certs” on “true”, the user will automatically be notified of his new connection, but **only if he is connected to the same server at that moment.**

FTS will:

- Create a system User (e.g. Joe)
- Generate valid Certifications
- Package the certs into a zip file with the same name of the user (e.g. Joe.zip)
- Create a private Data Package. This can be seen in the Mission section, with the other Data Packages
- Send the private DP automatically to a ATAK/Wintak (or compatible client)
- To the user with the same name (Joe)
The user will receive a notification of the reception
- Under “manage server connection” a new entry with the name `FreeTAKServer_[SERVERIP]` will appear.
- The user needs to activate the connection (in WinTAK he may need to restart the software)

Since ATAK 4.6 the ability to use non secured data packages has been disabled.

5.1.2 Alternate certificates distribution


If the user is not online at the moment of the certs creations, it's possible to deploy the certifications by:

- Download the data package and use another type of secure transportation
- As soon the user is online, set the certification Data Package to be public, allowing the user to download it and then changing it back to private

5.1.3 Deactivate Certification

Since FTS 1.9 it's possible to deactivate a certification by **deleting the associated user**. The next time the user tries to connect to the server using the certifications, will get an `IO error`.

5.2 Group Permissions



Future functionality, not currently active.

Allows to create and assign permission to groups. When activated, will filter what an user can receive from FTS.

6.0 Connect

A menu that can be used to create Center Of Target (CoTs) using a “Human API” and send system messages to FTS users. This is a User interface to some of the FTS Public UI (see https://freetakteam.github.io/FreeTAKServer-User-Docs/API/REST_APIDoc.html for complete description of the API)

6.1 Send CoT

Can be used to create a CoT (also called a geoObject)

fill out the fields with the desired values.

- **Name:** geoObject name that will display on map
- **Longitude/Latitude:** Determines where the object will appear
- **Attitude:** Sets the colour and external shape (and thus faction) of the geoObject based on MILSTD 2525D
- **GeoObject:** Changes the shape and type of the object (ex: sniper, grenadier)
- **Timeout:** The length of time the object appears, measured in seconds

6.2 Emergency

Allows to see, delete and create new emergencies on the server

- **Delete:** This can be done by selecting the undesired data packages and then clicking on “delete” (bottom right)
- **Add:** Start by clicking the “add” button at bottom right. An extension of the panel will appear. Simply fill out the pertinent information (name, location in longitude/latitude, type of emergency). Press “send” once finished


6.3 Manage Presence

Using this function, the user can create a custom team member (friendly Dot) on the ATAK map, who will however appear like a real TAK user.

To create a new member simply fill out the fields with the proper information. Once finished, press “send” (bottom right of panel).

6.4 Message

This function allows users to send system messages to all connected TAK clients.



The screenshot shows a dark-themed user interface for sending a message. At the top right, there is a label "[MESSAGE]". Below it is a large text input field containing the placeholder text "ex.The server will shutdown in 5 minutes...". Underneath the input field, on the left, is the label "Sender" followed by a smaller text input field. On the bottom right of the interface is a blue button labeled "Send".

To send a message it suffices to enter the message in the top field, and then specify the sender name in the field marked “sender”. Once finished, press “Send”.

7.0 Configure

Used to configure services and federated servers.

7.1 System Configuration

Here the services can be turned on and off and a port can be assigned to the service.

The Data Package IP is initially determined by the starting parameter of FTS.

```
sudo python3 -m FreeTAKServer.controllers.services.FTS -DataPackageIP
204.48.30.216 -AutoStart True
```

FTS supports following services:

- **TCP COT:** used when a client connects with regular TCP
- **SSL COT:** used when a client connects with an encrypted channel
- **HTTP DP:** Data package function over HTTP
- **SSL DP:** Data package function over an encrypted channel
- **API:** the Public REST API. Allows to send data over REST for integration with other systems. If deactivated some function of the WebUI will not work
- **FED:** Federation function, allow to create outgoing connections to other TAK servers

To turn a service on and off:

- click on the slider of the desired service
- Click 'apply'

To change a service port:

- Move the slider to stop the service
- Click 'apply'
- Change value of the port
- Click 'apply'
- Reactivate the service by moving the slider
- Click 'apply'

7.2 Outgoing Federations

See 4.4 Federations.

FTS 2.2 - User Manual

Name

Reconnect

30

Max Retries

3

Enabled

▼

[OUTGOING FEDERATION]

IP / Domain

Port

Fallback


lantern

▼

Apply

8.0 About

FTS and UI version notes and special thanks



7.1 About FTS

A description of the software

7.2 FTS and UI version

Current running version and IP, important when reporting bugs

7.3 Credits

A list of individuals and organization that have contributed to FTS

7.4 Open Source Note

A list of libraries and other projects being used