

These mapping tables are created with source code of Gecko and Chromium and testing with Edge.  
If you find something wrong, email me <masayuki@d-toybox.com>.

Meanings:

Perhaps or clearly, the value is buggy.

Incompatible values, but not sure which one is better.

Needs investigation.

Empty cell means that the value is still not sure.

[The key values are defined by UI Events KeyboardEvent key Values.](#)

	Gecko	Chromium	IE9
VK_LBUTTON (0x01)	"Unidentified"	"Unidentified"	"Unidentified"
VK_RBUTTON (0x02)	"Unidentified"	"Unidentified"	"Unidentified"
VK_CANCEL (0x03)	"Cancel"	"Cancel"	"
VK_MBUTTON (0x04)	"Unidentified"	"Unidentified"	"Unidentified"
VK_XBUTTON1 (0x05)	"Unidentified"	"Unidentified"	"Unidentified"
VK_XBUTTON2 (0x06)	"Unidentified"	"Unidentified"	"Unidentified"
VK_BACK (0x08)	"Backspace"	"Backspace"	"Backspace"
VK_TAB (0x09)	"Tab"	"Tab"	"Tab"
VK_CLEAR (0x0C)	"Clear"	"Clear"	"Clear"
VK_RETURN (0x0D)	"Enter"	"Enter"	"Enter"
VK_SHIFT (0x10)	"Shift"	"Shift"	"Shift"
VK_CONTROL (0x11)	"Control"	"Control"	"Control"
VK_MENU (0x12)	"Alt"	"Alt"	"Alt"
VK_PAUSE (0x13)	"Pause"	"Pause"	"Pause"
VK_CAPITAL (0x14)	"CapsLock"	"CapsLock"	"CapsLock"
VK_KANA, VK_HANGUEL, VK_HANGUL (0x15)	"KanaMode" for Japanese keyboard layout "HangulMode" for Korean keyboard layout "Unidentified" for the others	"KanaMode" for Japanese keyboard layout "HanguleMode" for Korean keyboard layout "Unidentified" for the others	"KanaMode"
VK_JUNJA (0x17)	"JunjaMode"	"JunjaMode"	"JunjaMode"
VK_FINAL (0x18)	"FinalMode"	"FinalMode"	"HanjaMode"
VK_HANJA, VK_KANJI (0x19)	"KanjiMode" for Japanese keyboard layout "HanjaMode" for Korean keyboard layout "Unidentified" for the others	"KanjiMode" for Japanese keyboard layout "HanjaMode" for Korean keyboard layout "Unidentified" for the others	"KanjiMode"
VK_ESCAPE (0x1B)	"Escape"	"Escape"	"Esc"
VK_CONVERT (0x1C)	"Convert"	"Convert"	"Convert"
VK_NONCONVERT (0x1D)	"NonConvert"	"NonConvert"	"Nonconvert"
VK_ACCEPT (0x1E)	"Accept"	"Accept"	"Accept"
VK_MODECHANGE (0x1F)	"ModeChange"	"ModeChange"	"ModeChange"
VK_SPACE (0x20)	Actual input character.		"Spacebar"
VK_PRIOR (0x21)	"PageUp"	"PageUp"	"PageUp"
VK_NEXT (0x22)	"PageDown"	"PageDown"	"PageDown"
VK_END (0x23)	"End"	"End"	"End"
VK_HOME (0x24)	"Home"	"Home"	"Home"
VK_LEFT (0x25)	"ArrowLeft"	"ArrowLeft"	"Left"
VK_UP (0x26)	"ArrowUp"	"ArrowUp"	"Up"
VK_RIGHT (0x27)	"ArrowRight"	"ArrowRight"	"Right"
VK_DOWN (0x28)	"ArrowDown"	"ArrowDown"	"Down"
VK_SELECT (0x29)	"Select"	"Select"	"Select"
VK_PRINT (0x2A)	"Unidentified"	"Print"	"Unidentified"
VK_EXECUTE (0x2B)	"Execute"	"Execute"	"Execute"
VK_SNAPSHOT (0x2C)	"PrintScreen"	"PrintScreen"	"PrintScreen"
VK_INSERT (0x2D)	"Insert"	"Insert"	"Insert"
VK_DELETE (0x2E)	"Delete"	"Delete"	"Del"
VK_HELP (0x2F)	"Help"	"Help"	"Help"
VK_LWIN (0x5B)	"OS"	"Meta"	"Win"
VK_RWIN (0x5C)	"OS"	"Meta"	"Win"
VK_APPS (0x5D)	"ContextMenu"	"ContextMenu"	"Apps"
VK_SLEEP (0x5F)	"Standby"	"Standby"	"Unidentified"
VK_MULTIPLY (0x6A)	Actual input character.		"Multiply"
VK_ADD (0x6B)	Actual input character.		"Add"
VK_SEPARATOR (0x6C)	Actual input character.		"Separator"
VK_SUBTRACT (0x6D)	Actual input character.		"Subtract"
VK_DECIMAL (0x6E)	Actual input character.		"Decimal"
VK_DIVIDE (0x6F)	Actual input character.		"Divide"
VK_F1 (0x70) ~ VK_F24 (0x87)	"F1" ~ "F24"	"F1" ~ "F24"	"F1" ~ "F24"
VK_NUMLOCK (0x90)	"NumLock"	"NumLock"	"NumLock"
VK_SCROLL (0x91)	"ScrollLock"	"ScrollLock"	"Scroll"
VK_LSHIFT (0xA0)	"Shift"	"Shift"	"Shift"
VK_RSHIFT (0xA1)	"Shift"	"Shift"	"Shift"
VK_LCONTROL (0xA2)	"Control"	"Control"	"Control"
VK_RCONTROL (0xA3)	"Control"	"Control"	"Control"
VK_LMENU (0xA4)	"Alt"	"Alt"	"Alt"
VK_RMENU (0xA5)	"Alt"	"Alt"	"Alt"
VK_BROWSER_BACK (0xA6)	"BrowserBack"	"BrowserBack"	"BrowserBack"
VK_BROWSER_FORWARD (0xA7)	"BrowserForward"	"BrowserForward"	"BrowserForward"
VK_BROWSER_REFRESH (0xA8)	"BrowserRefresh"	"BrowserRefresh"	"BrowserRefresh"
VK_BROWSER_STOP (0xA9)	"BrowserStop"	"BrowserStop"	"BrowserStop"
VK_BROWSER_SEARCH (0xAA)	"BrowserSearch"	"BrowserSearch"	"BrowserSearch"
VK_BROWSER_FAVORITES (0xAB)	"BrowserFavorites"	"BrowserFavorites"	"BrowserFavorites"
VK_BROWSER_HOME (0xAC)	"BrowserHome"	"BrowserHome"	"BrowserHome"
VK_VOLUME_MUTE (0xAD)	"AudioVolumeMute"	"AudioVolumeMute"	"VolumeMute"
VK_VOLUME_DOWN (0xAE)	"AudioVolumeDown"	"AudioVolumeDown"	"VolumeDown"
VK_VOLUME_UP (0xAF)	"AudioVolumeUp"	"AudioVolumeUp"	"VolumeUp"
VK_MEDIA_NEXT_TRACK (0xB0)	"MediaTrackNext"	"MediaTrackNext"	"MediaNextTrack"
VK_MEDIA_PREV_TRACK (0xB1)	"MediaTrackPrevious"	"MediaTrackPrevious"	"MediaPreviousTrack"

	<a href="#">Gecko</a>	<a href="#">Chromium</a>	IE9
VK_MEDIA_STOP (0xB2)	"MediaStop"	"MediaStop"	"MediaStop"
VK_MEDIA_PLAY_PAUSE (0xB3)	"MediaPlayerPause"	"MediaPlayerPause"	"MediaPlayerPause"
VK_LAUNCH_MAIL (0xB4)	"LaunchMail"	"LaunchMail"	"LaunchMail"
VK_LAUNCH_MEDIA_SELECT (0xB5)	"LaunchMediaPlayer"	"LaunchMediaPlayer"	"SelectMedia"
VK_LAUNCH_APP1 (0xB6)	"LaunchApplication1"	"LaunchMyComputer"	"LaunchApplication1"
VK_LAUNCH_APP2 (0xB7)	"LaunchApplication2"	"LaunchMyCalculator"	"LaunchApplication2"
VK_OEM_AX (0xE1)	"Unidentified"	"AltGraph"	
VK_PROCESSKEY (0xE5)	"Unidentified"	"Process"	"Unidentified" (tested without IME)
VK_PACKET (0xE7)	"Unidentified"	"Unidentified"	U+0000(null character at 1st, tested without SendInput() API)
VK_OEM_RESET (0xE9)	"Unidentified"	"Unidentified"	"Unidentified"
VK_OEM_JUMP (0xEA)	"Unidentified"	"Unidentified"	"Unidentified"
VK_OEM_PA1 (0xEB)	"Unidentified"	"Unidentified"	"Unidentified"
VK_OEM_PA2 (0xEC)	"Unidentified"	"Unidentified"	"Unidentified"
VK_OEM_PA3 (0xED)	"Unidentified"	"Unidentified"	"Unidentified"
VK_OEM_WSCTRL (0xEE)	"Unidentified"	"Unidentified"	"Unidentified"
VK_OEM_CUSEL (0xEF)	"Unidentified"	"Unidentified"	"Unidentified"
VK_OEM_ATTN (0xF0)	"Alphanumeric" for Japanese keyboard layout "Unidentified" for the others	"Alphanumeric" for Japanese keyboard layout "Unidentified" for the others	"Unidentified"
VK_OEM_FINISH (0xF1)	"Katakana" for Japanese keyboard layout "Unidentified" for the others	"Katakana" for Japanese keyboard layout "Unidentified" for the others	"Unidentified"
VK_OEM_COPY (0xF2)	"Hiragana" for Japanese keyboard layout "Unidentified" for the others	"Hiragana" for Japanese keyboard layout "Unidentified" for the others	"Unidentified"
VK_OEM_AUTO, VK_DBE_SBCSCHAR (0xF3)	"Hankaku" for Japanese keyboard layout "Unidentified" for the others	"Hankaku" for Japanese keyboard layout "Unidentified" for the others	"Unidentified"
VK_OEM_ENLW, VK_DBE_DBCSCHAR (0xF4)	"Zenkaku" for Japanese keyboard layout "Unidentified" for the others	"Zenkaku" for Japanese keyboard layout "Unidentified" for the others	"Unidentified"
VK_OEM_BACKTAB (0xF5)	"Romaji" for Japanese keyboard layout "Unidentified" for the others	"Romaji" for Japanese keyboard layout "Unidentified" for the others	"Unidentified"
VK_ATTN (0xF6)	"KanaMode" for Japanese keyboard layout "Attn" for the others	"KanaMode" for Japanese keyboard layout "Attn" for the others	"Attn"
VK_CRSEL (0xF7)	"CrSel"	"CrSel"	"CrSel"
VK_EXSEL (0xF8)	"ExSel"	"ExSel"	"Exsel"
VK_EREOF (0xF9)	"EraseEof"	"EraseEof"	"EraseEof"
VK_PLAY (0xFA)	"Play"	"Play"	"Play"
VK_ZOOM (0xFB)	"ZoomToggle"	"ZoomToggle"	"Zoom"
VK_NONAME (0xFC)	"Unidentified"	"Unidentified"	"Unidentified"
VK_PA1 (0xFD)	"Unidentified"	"Unidentified"	"Unidentified"
VK_OEM_CLEAR (0xFE)	"Clear"	"Clear"	"Clear"

virtual keycode	<a href="#">Gecko</a>	<a href="#">Chromium</a>
kVK_ISO_Section (0x0A)	"Unidentified"	
kVK_Return (0x24)	"Enter"	"Enter"
kVK_Tab (0x30)	"Tab"	"Tab"
kVK_Space (0x31)	Actual input character.	
kVK_Delete (0x33)	"Backspace"	"Backspace"
Enter key on keypad of PowerBook (0x34)	"Enter"	
kVK_Escape (0x35)	"Escape"	"Escape"
kVK_RightCommand (0x36)	"Meta"	"Meta"
kVK_Command (0x37)	"Meta"	"Meta"
kVK_Shift (0x38)	"Shift"	"Shift"
kVK_CapsLock (0x39)	"CapsLock"	"CapsLock"
kVK_Option (0x3A)	"Alt"	"Alt"
kVK_Control (0x3B)	"Control"	"Control"
kVK_RightShift (0x3C)	"Shift"	"Shift"
kVK_RightOption (0x3D)	"Alt"	"Alt"
kVK_RightControl (0x3E)	"Control"	"Control"
kVK_Function (0x3F)	"Fn"	"Fn"
kVK_F17 (0x40)	"F17"	"F17"
kVK_ANSI_KeypadDecimal (0x41)	Actual input character.	
kVK_ANSI_KeypadMultiply (0x43)	Actual input character.	
kVK_ANSI_KeypadPlus (0x45)	Actual input character.	
kVK_ANSI_KeypadClear (0x47)	"Clear"	
kVK_VolumeUp (0x48)	"VolumeUp"	"VolumeUp"
kVK_VolumeDown (0x49)	"VolumeDown"	"VolumeDown"
kVK_Mute (0x4A)	"VolumeMute"	"VolumeMute"
kVK_ANSI_KeypadDivide (0x4B)	Actual input character.	
kVK_ANSI_KeypadEnter (0x4C)	"Enter"	"Enter"
kVK_ANSI_KeypadMinus (0x4E)	Actual input character.	
kVK_F18 (0x4F)	"F18"	"F18"
kVK_F19 (0x50)	"F19"	"F19"
kVK_ANSI_KeypadEquals (0x51)	Actual input character.	
kVK_ANSI_Keypad0 (0x52)	Actual input character.	
kVK_ANSI_Keypad1 (0x53)	Actual input character.	
kVK_ANSI_Keypad2 (0x54)	Actual input character.	
kVK_ANSI_Keypad3 (0x55)	Actual input character.	
kVK_ANSI_Keypad4 (0x56)	Actual input character.	
kVK_ANSI_Keypad5 (0x57)	Actual input character.	
kVK_ANSI_Keypad6 (0x58)	Actual input character.	
kVK_ANSI_Keypad7 (0x59)	Actual input character.	
kVK_F20 (0x5A)	"F20"	"F20"
kVK_ANSI_Keypad8 (0x5B)	Actual input character.	
kVK_ANSI_Keypad9 (0x5C)	Actual input character.	

virtual keycode	<a href="#">Gecko</a>	<a href="#">Chromium</a>
<b>kVK_JIS_KeypadComma (0x5F)</b>	Actual input character.	
<b>kVK_F5 (0x60)</b>	"F5"	"F5"
<b>kVK_F6 (0x61)</b>	"F6"	"F6"
<b>kVK_F7 (0x62)</b>	"F7"	"F7"
<b>kVK_F3 (0x63)</b>	"F3"	"F3"
<b>kVK_F8 (0x64)</b>	"F8"	"F8"
<b>kVK_F9 (0x65)</b>	"F9"	"F9"
<b>kVK_JIS_Eisu (0x66)</b>	"Eisu"	
<b>kVK_F11 (0x67)</b>	"F11"	"F11"
<b>kVK_JIS_Kana (0x68)</b>	"KanjiMode"	
<b>kVK_F13 (0x69)</b>	"F13"	"F13"
<b>kVK_F16 (0x6A)</b>	"F16"	"F16"
<b>kVK_F14 (0x6B)</b>	"F14"	"F14"
<b>kVK_F10 (0x6D)</b>	"F10"	"F10"
<b>kVK_ContextMenu (0x6E)</b>	"Unidentified"	"ContextMenu"
<b>kVK_F12 (0x6F)</b>	"F12"	"F12"
<b>kVK_F15 (0x71)</b>	"F15"	"F15"
<b>kVK_Help (0x72)</b>	"Help"	
<b>kVK_Home (0x73)</b>	"Home"	
<b>kVK_PageUp (0x74)</b>	"PageUp"	"PageUp"
<b>kVK_ForwardDelete (0x75)</b>	"Delete"	"Delete"
<b>kVK_F4 (0x76)</b>	"F4"	"F4"
<b>kVK_End (0x77)</b>	"End"	"End"
<b>kVK_F2 (0x78)</b>	"F2"	"F2"
<b>kVK_PageDown (0x79)</b>	"PageDown"	"PageDown"
<b>kVK_F1 (0x7A)</b>	"F1"	"F1"
<b>kVK_LeftArrow (0x7B)</b>	"ArrowLeft"	"ArrowLeft"
<b>kVK_RightArrow (0x7C)</b>	"ArrowRight"	"ArrowRight"
<b>kVK_DownArrow (0x7D)</b>	"ArrowDown"	"ArrowDown"
<b>kVK_UpArrow (0x7E)</b>	"ArrowUp"	"ArrowUp"

keysyms	<a href="#">Gecko</a>	<a href="#">Chromium</a>
<b>BackSpace (0xFF08)</b>	"Backspace"	"Backspace"
<b>Tab (0xFF09)</b>	"Tab"	"Tab"
<b>Linefeed (0xFF0A)</b>	"Unidentified"	"Enter"
<b>Clear (0xFF0B)</b>	"Clear"	"Clear"
<b>Return (0xFF0D)</b>	"Enter"	"Enter"
<b>Pause (0xFF13)</b>	"Pause"	"Pause"
<b>Scroll_Lock (0xFF14)</b>	"ScrollLock"	"ScrollLock"
<b>Sys_Req (0xFF15)</b>	"PrintScreen"	"Unidentified"
<b>Escape (0xFF1B)</b>	"Escape"	"Escape"
<b>Delete (0xFFFF)</b>	"Delete"	"Delete"
<b>Multi_key (0xFF20)</b>	"Compose"	"Compose"
<b>Codeinput (0xFF37)</b>	"CodeInput"	"CodeInput"
<b>SingleCandidate (0xFF3C)</b>	"SingleCandidate"	"SingleCandidate"
<b>MultipleCandidate (0xFF3D)</b>	"AllCandidates"	"AllCandidates"
<b>PreviousCandidate (0xFF3E)</b>	"PreviousCandidate"	"PreviousCandidate"
<b>Kanji (0xFF21)</b>	"KanjiMode"	"KanjiMode"
<b>Muhenkan (0xFF22)</b>	"NonConvert"	"NonConvert"
<b>Henkan_Mode (0xFF23)</b>	"Convert"	"Convert"
<b>Romaji (0xFF24)</b>	"Romaji"	"Romaji"
<b>Hiragana (0xFF25)</b>	"Hiragana"	"Hiragana"
<b>Katakana (0xFF26)</b>	"Katakana"	"Katakana"
<b>Hiragana_Katakana (0xFF27)</b>	"HiraganaKatakana"	"HiraganaKatakana"
<b>Zenkaku (0xFF28)</b>	"Zenkaku"	"Zenkaku"
<b>Hankaku (0xFF29)</b>	"Hankaku"	"Hankaku"
<b>Zenkaku_Hankaku (0xFF2A)</b>	"ZenkakuHankaku"	"ZenkakuHankaku"
<b>Touroku (0xFF2B)</b>	"Unidentified"	"Unidentified"
<b>Massyo (0xFF2C)</b>	"Unidentified"	"Unidentified"
<b>Kana_Lock (0xFF2D)</b>	"KanaMode"	"KanaMode"
<b>Kana_Shift (0xFF2E)</b>	"KanaMode"	"Unidentified"
<b>Eisu_Shift (0xFF2F)</b>	"Alphanumeric"	"Eisu"
<b>Eisu_toggle (0xFF30)</b>	"Alphanumeric"	"Eisu"
<b>Home (0xFF50)</b>	"Home"	"Home"
<b>Left (0xFF51)</b>	"ArrowLeft"	"ArrowLeft"
<b>Up (0xFF52)</b>	"ArrowUp"	"ArrowUp"
<b>Right (0xFF53)</b>	"ArrowRight"	"ArrowRight"
<b>Down (0xFF54)</b>	"ArrowDown"	"ArrowDown"
<b>Prior (0xFF55)</b>	"PageUp"	"PageUp"
<b>Next (0xFF56)</b>	"PageDown"	"PageDown"
<b>End (0xFF57)</b>	"End"	"End"
<b>Begin (0xFF58)</b>	"Unidentified"	"Unidentified"
<b>Select (0xFF60)</b>	"Select"	"Select"
<b>Print (0xFF61)</b>	"PrintScreen"	"Print"

keysyms	<a href="#">Gecko</a>	<a href="#">Chromium</a>
Execute (0xFF62)	"Execute"	"Execute"
Insert (0xFF63)	"Insert"	"Insert"
Undo (0xFF65)	"Undo"	"Undo"
Redo (0xFF66)	"Redo"	"Redo"
Menu (0xFF67)	"ContextMenu"	"ContextMenu"
Find (0xFF68)	"Find"	"Find"
Cancel (0xFF69)	"Cancel"	"Cancel"
Help (0xFF6A)	"Help"	"Help"
Break (0xFF6B)	"Pause"	"Attn"
Mode_switch (0xFF7E)	"AltGraph"	"ModeChange"
Num_Lock (0xFF7F)	"NumLock"	"NumLock"
KP_Tab (0xFF89)	"Tab"	"Tab"
KP_Enter (0xFF8D)	"Enter"	"Enter"
KP_F1 (0xFF91)	"F1"	"F1"
KP_F2 (0xFF92)	"F2"	"F2"
KP_F3 (0xFF93)	"F3"	"F3"
KP_F4 (0xFF94)	"F4"	"F4"
KP_Home (0xFF95)	"Home"	"Home"
KP_Left (0xFF96)	"ArrowLeft"	"ArrowLeft"
KP_Up (0xFF97)	"ArrowUp"	"ArrowUp"
KP_Right (0xFF98)	"ArrowRight"	"ArrowRight"
KP_Down (0xFF99)	"ArrowDown"	"ArrowDown"
KP_Prior (0xFF9A)	"PageUp"	"PageUp"
KP_Next (0xFF9B)	"PageDown"	"PageDown"
KP_End (0xFF9C)	"End"	"End"
KP_Begin (0xFF9D)	"Unidentified"	"Clear"
KP_Insert (0xFF9E)	"Insert"	"Insert"
KP_Delete (0xFF9F)	"Delete"	"Unidentified"
F1 ~ 24 (0xFFBE ~ 0xFFD5)	"F1" ~ "F24"	"F1" ~ "F24"
F25 ~ F35 (0xFFD6 ~ 0xFFE0)	"F25" ~ "F35"	"Unidentified"
Shift_L (0xFFE1)	"Shift"	"Shift"
Shift_R (0xFFE2)	"Shift"	"Shift"
Control_L (0xFFE3)	"Control"	"Control"
Control_R (0xFFE4)	"Control"	"Control"
Caps_Lock (0xFFE5)	"CapsLock"	"CapsLock"
Shift_Lock (0xFFE6)	<a href="#">"Shift"</a>	"Unidentified"
Meta_L (0xFFE7)	"Meta"	"Meta"
Meta_R (0xFFE8)	"Meta"	"Meta"
Alt_L (0xFFE9)	"Alt"	"Alt"
Alt_R (0xFFEA)	"Alt"	"Alt"
Super_L (0xFFEB)	<a href="#">"OS"</a>	<a href="#">"Meta"</a>
Super_R (0xFFEC)	<a href="#">"OS"</a>	<a href="#">"Meta"</a>

keysyms	<a href="#">Gecko</a>	<a href="#">Chromium</a>
Hyper_L (0xFFED)	"OS"	"Hyper"
Hyper_R (0xFFEE)	"OS"	"Hyper"
dead_hook (0xFE61)	"Dead"	
dead_horn (0xFE62)	"Dead"	
3270_Duplicate (0xFD01)	"Unidentified"	"Unidentified"
3270_FieldMark (0xFD02)	"Unidentified"	"Unidentified"
3270_Right2 (0xFD03)	"Unidentified"	"Unidentified"
3270_Left2 (0xFD04)	"Unidentified"	"Unidentified"
3270_BackTab (0xFD05)	"Unidentified"	"Unidentified"
3270_EraseEOF (0xFD06)	"EraseEof"	"EraseEof"
3270_EraseInput (0xFD07)	"Unidentified"	"Unidentified"
3270_Reset (0xFD08)	"Unidentified"	"Unidentified"
3270_Quit (0xFD09)	"Unidentified"	"Unidentified"
3270_PA1 (0xFD0A)	"Unidentified"	"Unidentified"
3270_PA2 (0xFD0B)	"Unidentified"	"Unidentified"
3270_PA3 (0xFD0C)	"Unidentified"	"Unidentified"
3270_Test (0xFD0D)	"Unidentified"	"Unidentified"
3270_Attn (0xFD0E)	"Attn"	"Attn"
3270_CursorBlink (0xFD0F)	"Unidentified"	"Unidentified"
3270_AltCursor (0xFD10)	"Unidentified"	"Unidentified"
3270_KeyClick (0xFD11)	"Unidentified"	"Unidentified"
3270_Jump (0xFD12)	"Unidentified"	"Unidentified"
3270_Ident (0xFD13)	"Unidentified"	"Unidentified"
3270_Rule (0xFD14)	"Unidentified"	"Unidentified"
3270_Copy (0xFD15)	"Unidentified"	"Unidentified"
3270_Play (0xFD16)	"Play"	"Play"
3270_Setup (0xFD17)	"Unidentified"	"Unidentified"
3270_Record (0xFD18)	"Unidentified"	"Unidentified"
3270_ChangeScreen (0xFD19)	"Unidentified"	"Unidentified"
3270_DeleteWord (0xFD1A)	"Unidentified"	"Unidentified"
3270_ExSelect (0xFD1B)	"ExSel"	"ExSel"
3270_CursorSelect (0xFD1C)	"CrSel"	"CrSel"
3270_PrintScreen (0xFD1D)	"PrintScreen"	"PrintScreen"
3270_Enter (0xFD1E)	"Enter"	"Unidentified"
XF86XK_ModeLock (0x1008FF01)	"Unidentified"	"Unidentified"
XF86XK_MonBrightnessUp (0x1008FF02)	"BrightnessUp"	"BrightnessUp"
XF86XK_MonBrightnessDown (0x1008FF03)	"BrightnessDown"	"BrightnessDown"
XF86XK_KbdLightOnOff (0x1008FF04)	"Unidentified"	"Unidentified"
XF86XK_KbdBrightnessUp (0x1008FF05)	"Unidentified"	"Unidentified"
XF86XK_KbdBrightnessDown (0x1008FF06)	"Unidentified"	"Unidentified"
XF86XK_Standby (0x1008FF10)	"Standby"	"Standby"
XF86XK_AudioLowerVolume (0x1008FF11)	"AudioVolumeDown"	"AudioVolumeDown"



keysyms	<a href="#">Gecko</a>	<a href="#">Chromium</a>
XF86XK_AudioMute (0x1008FF12)	"AudioVolumeMute"	"AudioVolumeMute"
XF86XK_AudioRaiseVolume (0x1008FF13)	"AudioVolumeUp"	"AudioVolumeUp"
XF86XK_AudioPlay (0x1008FF14)	"MediaPlay"	"MediaPlayPause"
XF86XK_AudioStop (0x1008FF15)	"MediaStop"	"MediaStop"
XF86XK_AudioPrev (0x1008FF16)	"MediaTrackPrevious"	"MediaTrackPrevious"
XF86XK_AudioNext (0x1008FF17)	"MediaTrackNext"	"MediaTrackNext"
XF86XK_HomePage (0x1008FF18)	"BrowserHome"	"BrowserHome"
XF86XK_Mail (0x1008FF19)	"LaunchMail"	"LaunchMail"
XF86XK_Start (0x1008FF1A)	"Unidentified"	"Unidentified"
XF86XK_Search (0x1008FF1B)	"BrowserSearch"	"BrowserSearch"
XF86XK_AudioRecord (0x1008FF1C)	"MediaRecord"	"MediaRecord"
XF86XK_Calculator (0x1008FF1D)	"LaunchCalculator"	"LaunchCalculator"
XF86XK_Memo (0x1008FF1E)	"Unidentified"	"Unidentified"
XF86XK_ToDoList (0x1008FF1F)	"Unidentified"	"Unidentified"
XF86XK_Calendar (0x1008FF20)	"LaunchCalendar"	"LaunchCalendar"
XF86XK_PowerDown (0x1008FF21)	"PowerOff"	"Unidentified"
XF86XK_ContrastAdjust (0x1008FF22)	"Unidentified"	"Unidentified"
XF86XK_RockerUp (0x1008FF23)	"Unidentified"	"Unidentified"
XF86XK_RockerDown (0x1008FF24)	"Unidentified"	"Unidentified"
XF86XK_RockerEnter (0x1008FF25)	"Unidentified"	"Unidentified"
XF86XK_Back (0x1008FF26)	"BrowserBack"	"BrowserBack"
XF86XK_Forward (0x1008FF27)	"BrowserForward"	"BrowserForward"
XF86XK_Stop (0x1008FF28)	"BrowserStop"	"BrowserStop"
XF86XK_Refresh (0x1008FF29)	"BrowserRefresh"	"BrowserRefresh"
XF86XK_PowerOff (0x1008FF2A)	"PowerOff"	"PowerOff"
XF86XK_WakeUp (0x1008FF2B)	"WakeUp"	"WakeUp"
XF86XK_Eject (0x1008FF2C)	"Eject"	"Eject"
XF86XK_ScreenSaver (0x1008FF2D)	"LaunchScreenSaver"	"LaunchScreenSaver"
XF86XK_WWW (0x1008FF2E)	"LaunchWebBrowser"	"LaunchWebBrowser"
XF86XK_Sleep (0x1008FF2F)	"Standby"	"Standby"
XF86XK_Favorites (0x1008FF30)	"Unidentified"	"BrowserFavorites"
XF86XK_AudioPause (0x1008FF31)	"MediaPause"	"MediaPause"
XF86XK_AudioMedia (0x1008FF32)	"LaunchMediaPlayer"	"LaunchMediaPlayer"
XF86XK_MyComputer (0x1008FF33)	"LaunchMyComputer"	"LaunchMyComputer"
XF86XK_VendorHome (0x1008FF34)	"Unidentified"	"Unidentified"
XF86XK_LightBulb (0x1008FF35)	"Unidentified"	"Unidentified"
XF86XK_Shop (0x1008FF36)	"Unidentified"	"Unidentified"
XF86XK_History (0x1008FF37)	"Unidentified"	"Unidentified"
XF86XK_OpenURL (0x1008FF38)	"Unidentified"	"Unidentified"
XF86XK_AddFavorite (0x1008FF39)	"Unidentified"	"Unidentified"
XF86XK_HotLinks (0x1008FF3A)	"Unidentified"	"Unidentified"
XF86XK_BrightnessAdjust (0x1008FF3B)	"Dimmer"	"Unidentified"

keysyms	<a href="#">Gecko</a>	<a href="#">Chromium</a>
XF86XK_Finance (0x1008FF3C)	"Unidentified"	"Unidentified"
XF86XK_Community (0x1008FF3D)	"Unidentified"	"Unidentified"
XF86XK_AudioRewind (0x1008FF3E)	"MediaRewind"	"MediaRewind"
XF86XK_BackForward (0x1008FF3F)	"Unidentified"	"Unidentified"
XF86XK_Launch0 (0x1008FF40)	"LaunchApplication1"	"Unidentified"
XF86XK_Launch1 (0x1008FF41)	"LaunchApplication2"	"Unidentified"
XF86XK_Launch2 (0x1008FF42)	"LaunchApplication3"	"Unidentified"
XF86XK_Launch3 (0x1008FF43)	"LaunchApplication4"	"Unidentified"
XF86XK_Launch4 (0x1008FF44)	"LaunchApplication5"	"F14"
XF86XK_Launch5 (0x1008FF45)	"LaunchApplication6"	"F15"
XF86XK_Launch6 (0x1008FF46)	"LaunchApplication7"	"F16"
XF86XK_Launch7 (0x1008FF47)	"LaunchApplication8"	"F17"
XF86XK_Launch8 (0x1008FF48)	"LaunchApplication9"	"F18"
XF86XK_Launch9 (0x1008FF49)	"LaunchApplication10"	"Unidentified"
XF86XK_LaunchA (0x1008FF4A)	"LaunchApplication11"	"Unidentified"
XF86XK_LaunchB (0x1008FF4B)	"LaunchApplication12"	"Unidentified"
XF86XK_LaunchC (0x1008FF4C)	"LaunchApplication13"	"Unidentified"
XF86XK_LaunchD (0x1008FF4D)	"LaunchApplication14"	"Unidentified"
XF86XK_LaunchE (0x1008FF4E)	"LaunchApplication15"	"Unidentified"
XF86XK_LaunchF (0x1008FF4F)	"LaunchApplication16"	"Unidentified"
XF86XK_ApplicationLeft (0x1008FF50)	"Unidentified"	"Unidentified"
XF86XK_ApplicationRight (0x1008FF51)	"Unidentified"	"Unidentified"
XF86XK_Book (0x1008FF52)	"Unidentified"	"Unidentified"
XF86XK_CD (0x1008FF53)	"LaunchMediaPlayer"	"LaunchMediaPlayer"
XF86XK_Calculator (0x1008FF54)	"LaunchCalculator"	"LaunchCalculator"
XF86XK_Clear (0x1008FF55) (GDK_KEY_WindowClear)	"Unidentified"	"Clear"
XF86XK_Close (0x1008FF56)	"Close"	"Close"
XF86XK_Copy (0x1008FF57)	"Copy"	"Copy"
XF86XK_Cut (0x1008FF58)	"Cut"	"Cut"
XF86XK_Display (0x1008FF59)	"Unidentified"	"DisplaySwap"
XF86XK_DOS (0x1008FF5A)	"Unidentified"	"Unidentified"
XF86XK_Documents (0x1008FF5B)	"Unidentified"	"Unidentified"
XF86XK_Excel (0x1008FF5C)	"LaunchSpreadsheet"	"LaunchSpreadsheet"
XF86XK_Explorer (0x1008FF5D)	"LaunchMyComputer"	"LaunchMyComputer"
XF86XK_Game (0x1008FF5E)	"Unidentified"	"Unidentified"
XF86XK_Go (0x1008FF5F)	"Unidentified"	"Unidentified"
XF86XK_iTouch (0x1008FF60)	"Unidentified"	"Unidentified"
XF86XK_LogOff (0x1008FF61)	"LogOff"	"LogOff"
XF86XK_Market (0x1008FF62)	"Unidentified"	"Unidentified"
XF86XK_Meeting (0x1008FF63)	"Unidentified"	"Unidentified"
XF86XK_MenuKB (0x1008FF65)	"Unidentified"	"Unidentified"
XF86XK_MenuPB (0x1008FF66)	"Unidentified"	"Unidentified"

keysyms	<a href="#">Gecko</a>	<a href="#">Chromium</a>
XF86XK_MySites (0x1008FF67)	"Unidentified"	"Unidentified"
XF86XK_New (0x1008FF68)	"New"	"New"
XF86XK_News (0x1008FF69)	"Unidentified"	"Unidentified"
XF86XK_OfficeHome (0x1008FF6A)	"Unidentified"	"LaunchWordProcessor"
XF86XK_Open (0x1008FF6B)	"Open"	"Open"
XF86XK_Option (0x1008FF6C)	"Unidentified"	"Unidentified"
XF86XK_Paste (0x1008FF6D)	"Paste"	"Paste"
XF86XK_Phone (0x1008FF6E)	"Unidentified"	"Unidentified"
XF86XK_Q (0x1008FF70)	<i>not in GDK</i>	"Unidentified"
XF86XK_Reply (0x1008FF72)	"MailReply"	"MailReply"
XF86XK_Reload (0x1008FF73)	"BrowserRefresh"	"BrowserRefresh"
XF86XK_RotateWindows (0x1008FF74)	"Unidentified"	"Unidentified"
XF86XK_RotationPB (0x1008FF75)	"Unidentified"	"Unidentified"
XF86XK_RotationKB (0x1008FF76)	"Unidentified"	"Unidentified"
XF86XK_Save (0x1008FF77)	"Save"	"Save"
XF86XK_ScrollUp (0x1008FF78)	"Unidentified"	"End"
XF86XK_ScrollDown (0x1008FF79)	"Unidentified"	"PageDown"
XF86XK_ScrollClick (0x1008FF7A)	"Unidentified"	"Unidentified"
XF86XK_Send (0x1008FF7B)	"MailSend"	"MailSend"
XF86XK_Spell (0x1008FF7C)	"SpellCheck"	"SpellCheck"
XF86XK_SplitScreen (0x1008FF7D)	"Unidentified"	"SplitScreenToggle"
XF86XK_Support (0x1008FF7E)	"Unidentified"	"Unidentified"
XF86XK_TaskPane (0x1008FF7F)	"Unidentified"	"Unidentified"
XF86XK_Terminal (0x1008FF80)	"Unidentified"	"Unidentified"
XF86XK_Tools (0x1008FF81)	"Unidentified"	"F13"
XF86XK_Travel (0x1008FF82)	"Unidentified"	"Unidentified"
XF86XK_UserPB (0x1008FF84)	"Unidentified"	"Unidentified"
XF86XK_User1KB (0x1008FF85)	"Unidentified"	"Unidentified"
XF86XK_User2KB (0x1008FF86)	"Unidentified"	"Unidentified"
XF86XK_Video (0x1008FF87)	"LaunchMediaPlayer"	"Unidentified"
XF86XK_WheelButton (0x1008FF88)	"Unidentified"	"Unidentified"
XF86XK_Word (0x1008FF89)	"LaunchWordProcesso"	"LaunchWordProcessor"
XF86XK_Xfer (0x1008FF8A)	"Unidentified"	"Unidentified"
XF86XK_ZoomIn (0x1008FF8B)	"ZoomIn"	"ZoomIn"
XF86XK_ZoomOut (0x1008FF8C)	"ZoomOut"	"ZoomOut"
XF86XK_Away (0x1008FF8D)	"Unidentified"	"Unidentified"
XF86XK_Messenger (0x1008FF8E)	"Unidentified"	"Unidentified"
XF86XK_WebCam (0x1008FF8F)	"LaunchWebCam"	"LaunchWebCam"
XF86XK_MailForward (0x1008FF90)	"MailForward"	"MailForward"
XF86XK_Pictures (0x1008FF91)	"Unidentified"	"Unidentified"
XF86XK_Music (0x1008FF92)	"LaunchMusicPlayer"	"LaunchMusicPlayer"
XF86XK_Battery (0x1008FF93)	"Unidentified"	"Unidentified"

keysyms	<a href="#">Gecko</a>	<a href="#">Chromium</a>
XF86XK_Bluetooth (0x1008FF94)	"Unidentified"	"Unidentified"
XF86XK_WLAN (0x1008FF95)	"Unidentified"	"Unidentified"
XF86XK_UWB (0x1008FF96)	"Unidentified"	"Unidentified"
XF86XK_AudioForward (0x1008FF97)	"MediaFastForward"	"MediaFastForward"
XF86XK_AudioRepeat (0x1008FF98)	"Unidentified"	"Unidentified"
XF86XK_AudioRandomPlay (0x1008FF99)	"RandomToggle"	"RandomToggle"
XF86XK_Subtitle (0x1008FF9A)	"Subtitle"	"Subtitle"
XF86XK_AudioCycleTrack (0x1008FF9B)	"Unidentified"	"Unidentified"
XF86XK_CycleAngle (0x1008FF9C)	"Unidentified"	"Unidentified"
XF86XK_FrameBack (0x1008FF9D)	"Unidentified"	"Unidentified"
XF86XK_FrameForward (0x1008FF9E)	"Unidentified"	"Unidentified"
XF86XK_Time (0x1008FF9F)	"Unidentified"	"Unidentified"
XF86XK_Select (0x1008FFA0) (GDK_KEY_SelectButton)	"Unidentified"	"Unidentified"
XF86XK_View (0x1008FFA1)	"Unidentified"	"Unidentified"
XF86XK_TopMenu (0x1008FFA2)	"Unidentified"	"Unidentified"
XF86XK_Red (0x1008FFA3)	"ColorF0Red"	"Unidentified"
XF86XK_Green (0x1008FFA4)	"ColorF1Green"	"Unidentified"
XF86XK_Yellow (0x1008FFA5)	"ColorF2Yellow"	"Unidentified"
XF86XK_Blue (0x1008FFA6)	"ColorF3Blue"	"Unidentified"
XF86XK_Suspend (0x1008FFA7)	"Standby"	"Standby"
XF86XK_Hibernate (0x1008FFA8)	"Hibernate"	"Hibernate"
XF86XK_TouchpadToggle (0x1008FFA9)	"Unidentified"	"Unidentified"
XF86XK_TouchpadOn (0x1008FFB0)	<i>not in GDK</i>	"Unidentified"
XF86XK_TouchpadOff (0x1008FFB1)	<i>not in GDK</i>	"Unidentified"
XF86XK_AudioMicMute (0x1008FFB2)	<i>not in GDK</i>	"Unidentified"
XF86XK_Switch_VT_1 (0x1008FE01)	"Unidentified"	"Unidentified"
XF86XK_Switch_VT_2 (0x1008FE02)	"Unidentified"	"Unidentified"
XF86XK_Switch_VT_3 (0x1008FE03)	"Unidentified"	"Unidentified"
XF86XK_Switch_VT_4 (0x1008FE04)	"Unidentified"	"Unidentified"
XF86XK_Switch_VT_5 (0x1008FE05)	"Unidentified"	"Unidentified"
XF86XK_Switch_VT_6 (0x1008FE06)	"Unidentified"	"Unidentified"
XF86XK_Switch_VT_7 (0x1008FE07)	"Unidentified"	"Unidentified"
XF86XK_Switch_VT_8 (0x1008FE08)	"Unidentified"	"Unidentified"
XF86XK_Switch_VT_9 (0x1008FE09)	"Unidentified"	"Unidentified"
XF86XK_Switch_VT_10 (0x1008FE0A)	"Unidentified"	"Unidentified"
XF86XK_Switch_VT_11 (0x1008FE0B)	"Unidentified"	"Unidentified"
XF86XK_Switch_VT_12 (0x1008FE0C)	"Unidentified"	"Unidentified"
XF86XK_Ungrab (0x1008FE20)	"Unidentified"	"Unidentified"
XF86XK_ClearGrab (0x1008FE21)	"Unidentified"	"Unidentified"
XF86XK_Next_VMode (0x1008FE22)	"VideoModeNext"	"Unidentified"
XF86XK_Prev_VMode (0x1008FE23)	"Unidentified"	"Unidentified"
XF86XK_LogWindowTree (0x1008FE24)	<i>not in GDK</i>	"Unidentified"

keysyms	<a href="#">Gecko</a>	<a href="#">Chromium</a>
<b>XF86XK_LogGrabInfo (0x1008FE25)</b>	<i>not in GDK</i>	"Unidentified"
<b>ISO_Level3_Shift</b>		"AltGraph"
<b>ISO_Level3_Latch</b>		"AltGraph"
<b>ISO_Level5_Shift</b>		"Level5"
<b>ISO_Next_Group</b>		"GroupNext"
<b>ISO_Prev_Group</b>		"GroupPrevious"
<b>ISO_First_Group</b>		"GroupFirst"
<b>ISO_Last_Group</b>		"GroupLast"

virtual keycode	Gecko	Chromium	Spec	Notes
AKEYCODE_UNKNOWN (0)	"Unidentified"	"Unidentified"		
AKEYCODE_SOFT_LEFT (1)	"Unidentified"	"Unidentified"		
AKEYCODE_SOFT_RIGHT (2)	"Unidentified"	"Unidentified"		
AKEYCODE_HOME (3)	"GoHome"	"GoHome"	"GoHome"	Chromium fixed in crrev.com/2501083002
AKEYCODE_BACK (4)	"GoBack"	"GoBack"	"GoBack"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (3)
AKEYCODE_CALL (5)	"Call"	"Call"	"Call"	Chromium fixed in crrev.com/2501083002
AKEYCODE_ENDCALL (6)	"EndCall"	"EndCall"	"EndCall"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_0 (7) ~ AKEYCODE_9 (16)	Actual input character.	Actual input character.		
AKEYCODE_STAR (17)	Actual input character.	Actual input character.		
AKEYCODE_POUND (18)	Actual input character.	Actual input character.		
AKEYCODE_DPAD_UP (19)	"ArrowUp"	"ArrowUp"	"ArrowUp"	
AKEYCODE_DPAD_DOWN (20)	"ArrowDown"	"ArrowDown"	"ArrowDown"	
AKEYCODE_DPAD_LEFT (21)	"ArrowLeft"	"ArrowLeft"	"ArrowLeft"	
AKEYCODE_DPAD_RIGHT (22)	"ArrowRight"	"ArrowRight"	"ArrowRight"	
AKEYCODE_DPAD_CENTER (23)	"Enter"	"Enter"	"Enter"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (3)
AKEYCODE_VOLUME_UP (24)	"AudioVolumeUp"	"AudioVolumeUp"	"AudioVolumeUp"	
AKEYCODE_VOLUME_DOWN (25)	"AudioVolumeDown"	"AudioVolumeDown"	"AudioVolumeDown"	
AKEYCODE_POWER (26)	"Power"	"Power"	"Power"	
AKEYCODE_CAMERA (27)	"Camera"	"Camera"	"Camera"	
AKEYCODE_CLEAR (28)	"Clear"	"Clear"		
AKEYCODE_A (29) ~ AKEYCODE_Z (54)	Actual input character.	Actual input character.		
AKEYCODE_COMMA (55)	Actual input character.	Actual input character.		
AKEYCODE_PERIOD (56)	Actual input character.	Actual input character.		
AKEYCODE_ALT_LEFT (57)	"Alt"	"Alt"		
AKEYCODE_ALT_RIGHT (58)	"Alt"	"Alt"		
AKEYCODE_SHIFT_LEFT (59)	"Shift"	"Shift"		
AKEYCODE_SHIFT_RIGHT (60)	"Shift"	"Shift"		
AKEYCODE_TAB (61)	"Tab"	"Tab"		
AKEYCODE_SPACE (62)	Actual input character.	Actual input character.		
AKEYCODE_SYM (63)	"Symbol"	"Symbol"		
AKEYCODE_EXPLORER (64)	"LaunchWebBrowser"	"LaunchWebBrowser"		
AKEYCODE_ENVELOPE (65)	"LaunchMail"	"LaunchMail"		
AKEYCODE_ENTER (66)	"Enter"	"Enter"		
AKEYCODE_DEL (67)	"Backspace"	"Backspace"		
AKEYCODE_GRAVE (68)	Actual input character.	Actual input character.		
AKEYCODE_MINUS (69)	Actual input character.	Actual input character.		
AKEYCODE_EQUALS (70)	Actual input character.	Actual input character.		
AKEYCODE_LEFT_BRACKET (71)	Actual input character.	Actual input character.		
AKEYCODE_RIGHT_BRACKET (72)	Actual input character.	Actual input character.		
AKEYCODE_BACKSLASH (73)	Actual input character.	Actual input character.		
AKEYCODE_SEMICOLON (74)	Actual input character.	Actual input character.		
AKEYCODE_APOSTROPHE (75)	Actual input character.	Actual input character.		
AKEYCODE_SLASH (76)	Actual input character.	Actual input character.		
AKEYCODE_AT (77)	Actual input character.	Actual input character.		
AKEYCODE_NUM (78)	"Unidentified"	"Unidentified"		
AKEYCODE_HEADSETHOOK (79)	"HeadsetHook"	"HeadsetHook"	"HeadsetHook"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_FOCUS (80)	"CameraFocus"	"CameraFocus"	"CameraFocus"	Chromium fixed in crrev.com/2501083002
AKEYCODE_PLUS (81)	Actual input character.	Actual input character.		
AKEYCODE_MENU (82)	"ContextMenu"	"ContextMenu"		
AKEYCODE_NOTIFICATION (83)	"Notification"	"Notification"	"Notification"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_SEARCH (84)	"BrowserSearch"	"BrowserSearch"		
AKEYCODE_MEDIA_PLAY_PAUSE (85)	"MediaPlayPause"	"MediaPlayPause"	"MediaPlayPause"	
AKEYCODE_MEDIA_STOP (86)	"MediaStop"	"MediaStop"	"MediaStop"	
AKEYCODE_MEDIA_NEXT (87)	"MediaTrackNext"	"MediaTrackNext"	"MediaTrackNext"	
AKEYCODE_MEDIA_PREVIOUS (88)	"MediaTrackPrevious"	"MediaTrackPrevious"	"MediaTrackPrevious"	
AKEYCODE_MEDIA_REWIND (89)	"MediaRewind"	"MediaRewind"	"MediaRewind"	
AKEYCODE_MEDIA_FAST_FORWARD (90)	"MediaFastForward"	"MediaFastForward"	"MediaFastForward"	
AKEYCODE_MUTE (91)	"MicrophoneVolumeMute"	"MicrophoneVolumeMute"	"MicrophoneVolumeMute"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_PAGE_UP (92)	"PageUp"	"PageUp"		
AKEYCODE_PAGE_DOWN (93)	"PageDown"	"PageDown"		
AKEYCODE_PICTSYMBOLS (94)	"Unidentified"	"Unidentified"		
AKEYCODE_SWITCH_CHARSET (95)	"ModeChange"	"ModeChange"		Chromium fixed in crrev.com/2481033007
AKEYCODE_BUTTON_A (96)	"Unidentified"	"Unidentified"		
AKEYCODE_BUTTON_B (97)	"Unidentified"	"Unidentified"		
AKEYCODE_BUTTON_C (98)	"Unidentified"	"Unidentified"		
AKEYCODE_BUTTON_X (99)	"Unidentified"	"Unidentified"		
AKEYCODE_BUTTON_Y (100)	"Unidentified"	"Unidentified"		
AKEYCODE_BUTTON_Z (101)	"Unidentified"	"Unidentified"		
AKEYCODE_BUTTON_L1 (102)	"Unidentified"	"Unidentified"		
AKEYCODE_BUTTON_R1 (103)	"Unidentified"	"Unidentified"		
AKEYCODE_BUTTON_L2 (104)	"Unidentified"	"Unidentified"		
AKEYCODE_BUTTON_R2 (105)	"Unidentified"	"Unidentified"		
AKEYCODE_BUTTON_THUMBL (106)	"Unidentified"	"Unidentified"		
AKEYCODE_BUTTON_THUMBR (107)	"Unidentified"	"Unidentified"		
AKEYCODE_BUTTON_START (108)	"Unidentified"	"Unidentified"		
AKEYCODE_BUTTON_SELECT (109)	"Unidentified"	"Unidentified"		
AKEYCODE_BUTTON_MODE (110)	"Unidentified"	"Unidentified"		
AKEYCODE_ESCAPE (111)	"Escape"	"Escape"		
AKEYCODE_FORWARD_DEL (112)	"Delete"	"Delete"		
AKEYCODE_CTRL_LEFT (113)	"Control"	"Control"		
AKEYCODE_CTRL_RIGHT (114)	"Control"	"Control"		
AKEYCODE_CAPS_LOCK (115)	"CapsLock"	"CapsLock"		
AKEYCODE_SCROLL_LOCK (116)	"ScrollLock"	"ScrollLock"		
AKEYCODE_META_LEFT (117)	"Meta"	"Meta"		
AKEYCODE_META_RIGHT (118)	"Meta"	"Meta"		
AKEYCODE_FUNCTION (119)	"Fn"	"Fn"		
AKEYCODE_SYSRQ (120)	"PrintScreen"	"PrintScreen"		
AKEYCODE_BREAK (121)	"Pause"	"Pause"		
AKEYCODE_MOVE_HOME (122)	"Home"	"Home"	"Home"	
AKEYCODE_MOVE_END (123)	"End"	"End"	"End"	
AKEYCODE_INSERT (124)	"Insert"	"Insert"	"Insert"	
AKEYCODE_FORWARD (125)	"BrowserForward"	"BrowserForward"		Chromium fixed in crrev.com/2481033007
AKEYCODE_MEDIA_PLAY (126)	"MediaPlayer"	"MediaPlayer"	"MediaPlayer"	

virtual keycode	Gecko	Chromium	Spec	Notes
AKEYCODE_MEDIA_PAUSE (127)	"MediaPause"	"MediaPause"	"MediaPause"	
AKEYCODE_MEDIA_CLOSE (128)	"Unidentified"	"Close"	"Close"	
AKEYCODE_MEDIA_EJECT (129)	"Eject"	"Eject"	"Eject"	
AKEYCODE_MEDIA_RECORD (130)	"MediaRecord"	"MediaRecord"	"MediaRecord"	
AKEYCODE_F1 (131) ~ AKEYCODE_F12 (142)	"F1" ~ "F12"	"F1" ~ "F12"	"F1" ~ "F12"	
AKEYCODE_NUM_LOCK (143)	"NumLock"	"NumLock"	"NumLock"	
AKEYCODE_NUMPAD_0 (144) ~ AKEYCODE_NUMPAD_9 (153)	Actual input character.	Actual input character.	Actual input character.	
AKEYCODE_NUMPAD_DIVIDE (154)	Actual input character.	Actual input character.	Actual input character.	
AKEYCODE_NUMPAD_MULTIPLY (155)	Actual input character.	Actual input character.	Actual input character.	
AKEYCODE_NUMPAD_SUBTRACT (156)	Actual input character.	Actual input character.	Actual input character.	
AKEYCODE_NUMPAD_ADD (157)	Actual input character.	Actual input character.	Actual input character.	
AKEYCODE_NUMPAD_DOT (158)	Actual input character.	Actual input character.	Actual input character.	
AKEYCODE_NUMPAD_COMMA (159)	Actual input character.	Actual input character.	Actual input character.	
AKEYCODE_NUMPAD_ENTER (160)	"Enter"	"Enter"	"Enter"	Chromium fixed in crrev.com/2481033007
AKEYCODE_NUMPAD_EQUALS (161)	Actual input character.	Actual input character.	Actual input character.	
AKEYCODE_NUMPAD_LEFT_PAREN (162)	Actual input character.	Actual input character.	Actual input character.	
AKEYCODE_NUMPAD_RIGHT_PAREN (163)	Actual input character.	Actual input character.	Actual input character.	
AKEYCODE_VOLUME_MUTE (164)	"AudioVolumeMute"	"AudioVolumeMute"	"AudioVolumeMute"	
AKEYCODE_INFO (165)	"Info"	"Info"	"Info"	
AKEYCODE_CHANNEL_UP (166)	"ChannelUp"	"ChannelUp"	"ChannelUp"	
AKEYCODE_CHANNEL_DOWN (167)	"ChannelDown"	"ChannelDown"	"ChannelDown"	
AKEYCODE_ZOOM_IN (168)	"ZoomIn"	"ZoomIn"	"ZoomIn"	
AKEYCODE_ZOOM_OUT (169)	"ZoomOut"	"ZoomOut"	"ZoomOut"	
AKEYCODE_TV (170)	"TV"	"TV"	"TV"	
AKEYCODE_WINDOW (171)	"PinPToggle"	"Unidentified"	"Unidentified"	
AKEYCODE_GUIDE (172)	"Guide"	"Guide"	"Guide"	
AKEYCODE_DVR (173)	"DVR"	"Unidentified"	"DVR"	Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_BOOKMARK (174)	"BrowserFavorites"	"BrowserFavorites"	"BrowserFavorites"	Chromium fixed in crrev.com/2481033007
AKEYCODE_CAPTIONS (175)	"ClosedCaptionToggle"	"ClosedCaptionToggle"	"ClosedCaptionToggle"	Gecko fixed in bugzil.la/1274503 (3)
AKEYCODE_SETTINGS (176)	"Settings"	"Settings"	"Settings"	
AKEYCODE_TV_POWER (177)	"TVPower"	"TVPower"	"TVPower"	
AKEYCODE_TV_INPUT (178)	"TVInput"	"TVInput"	"TVInput"	
AKEYCODE_STB_POWER (179)	"STBPower"	"STBPower"	"STBPower"	
AKEYCODE_STB_INPUT (180)	"STBInput"	"STBInput"	"STBInput"	
AKEYCODE_AVR_POWER (181)	"AVRPower"	"AVRPower"	"AVRPower"	
AKEYCODE_AVR_INPUT (182)	"AVRInput"	"AVRInput"	"AVRInput"	
AKEYCODE_PROG_RED (183)	"ColorF0Red"	"ColorF0Red"	"ColorF0Red"	
AKEYCODE_PROG_GREEN (184)	"ColorF1Green"	"ColorF1Green"	"ColorF1Green"	
AKEYCODE_PROG_YELLOW (185)	"ColorF2Yellow"	"ColorF2Yellow"	"ColorF2Yellow"	
AKEYCODE_PROG_BLUE (186)	"ColorF3Blue"	"ColorF3Blue"	"ColorF3Blue"	
AKEYCODE_APP_SWITCH (187)	"AppSwitch"	"AppSwitch"	"AppSwitch"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_BUTTON_1 (188) ~ AKEYCODE_BUTTON_16 (203)	"Unidentified"	"Unidentified"	"Unidentified"	
AKEYCODE_LANGUAGE_SWITCH (204)	"GroupNext"	"GroupNext"	"GroupNext"	Chromium fixed in crrev.com/2481033007
AKEYCODE_MANNER_MODE (205)	"MannerMode"	"MannerMode"	"MannerMode"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_3D_MODE (206)	"TV3DMode"	"TV3DMode"	"TV3DMode"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_CONTACTS (207)	"LaunchContacts"	"LaunchContacts"	"LaunchContacts"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_CALENDAR (208)	"LaunchCalendar"	"LaunchCalendar"	"LaunchCalendar"	
AKEYCODE_MUSIC (209)	"LaunchMusicPlayer"	"LaunchMusicPlayer"	"LaunchMusicPlayer"	
AKEYCODE_CALCULATOR (210)	"LaunchCalculator"	"LaunchCalculator"	"LaunchCalculator"	
AKEYCODE_ZENKAKU_HANKAKU (211)	"ZenkakuHankaku"	"ZenkakuHankaku"	"ZenkakuHankaku"	
AKEYCODE_EISU (212)	"Eisu"	"Eisu"	"Eisu"	
AKEYCODE_MUHENKAN (213)	"NonConvert"	"NonConvert"	"NonConvert"	Chromium fixed in crrev.com/2481033007
AKEYCODE_HENKAN (214)	"Convert"	"Convert"	"Convert"	Chromium fixed in crrev.com/2481033007
AKEYCODE_KATAKANA_HIRAGANA (215)	"Hiraganakatakana"	"Hiraganakatakana"	"Hiraganakatakana"	
AKEYCODE_YEN (216)	Actual input character.	"Unidentified"	"Unidentified"	
AKEYCODE_RO (217)	Actual input character.	"Unidentified"	"Unidentified"	
AKEYCODE_KANA (218)	"KanjMode"	"KanaMode"	"KanaMode"	Chromium fixed in crrev.com/2501083002
AKEYCODE_ASSIST (219)	"Unidentified"	"Unidentified"	"Unidentified"	Gecko fixed in bugzil.la/1274503 (1)
AKEYCODE_BRIGHTNESS_DOWN (220)	"BrightnessDown"	"BrightnessDown"	"BrightnessDown"	Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_BRIGHTNESS_UP (221)	"BrightnessUp"	"BrightnessUp"	"BrightnessUp"	Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_MEDIA_AUDIO_TRACK (222)	"MediaAudioTrack"	"MediaAudioTrack"	"MediaAudioTrack"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_SLEEP (223)	"Standby"	"Standby"	"Standby"	Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_WAKEUP (224)	"WakeUp"	"WakeUp"	"WakeUp"	Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_PAIRING (225)	"Pairing"	"Pairing"	"Pairing"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_MEDIA_TOP_MENU (226)	"MediaTopMenu"	"MediaTopMenu"	"MediaTopMenu"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_11 (227)	"Unidentified"	"Unidentified"	"Unidentified"	
AKEYCODE_12 (228)	"Unidentified"	"Unidentified"	"Unidentified"	
AKEYCODE_LAST_CHANNEL (229)	"MediaLast"	"MediaLast"	"MediaLast"	Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_DATA_SERVICE (230)	"TVDataService"	"TVDataService"	"TVDataService"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_VOICE_ASSIST (231)	"Unidentified"	"Unidentified"	"Unidentified"	
AKEYCODE_TV_RADIO_SERVICE (232)	"TVRadioService"	"TVRadioService"	"TVRadioService"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_TELETEXT (233)	"Teletext"	"Teletext"	"Teletext"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_NUMBER_ENTRY (234)	"TVNumberEntry"	"TVNumberEntry"	"TVNumberEntry"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_TERRESTRIAL_ANALOG (235)	"TVTerrestrialAnalog"	"TVTerrestrialAnalog"	"TVTerrestrialAnalog"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_TERRESTRIAL_DIGITAL (236)	"TVTerrestrialDigital"	"TVTerrestrialDigital"	"TVTerrestrialDigital"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_SATELLITE (237)	"TVSatellite"	"TVSatellite"	"TVSatellite"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_SATELLITE_BS (238)	"TVSatelliteBS"	"TVSatelliteBS"	"TVSatelliteBS"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_SATELLITE_CS (239)	"TVSatelliteCS"	"TVSatelliteCS"	"TVSatelliteCS"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_SATELLITE_TOGGLE (240)	"TVSatelliteToggle"	"TVSatelliteToggle"	"TVSatelliteToggle"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_NETWORK (241)	"TVNetwork"	"TVNetwork"	"TVNetwork"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_ANTENNA_CABLE (242)	"TVAntennaCable"	"TVAntennaCable"	"TVAntennaCable"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_INPUT_HDMI_1 (243)	"TVInputHDMI1"	"TVInputHDMI1"	"TVInputHDMI1"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_INPUT_HDMI_2 (244)	"TVInputHDMI2"	"TVInputHDMI2"	"TVInputHDMI2"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_INPUT_HDMI_3 (245)	"TVInputHDMI3"	"TVInputHDMI3"	"TVInputHDMI3"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_INPUT_HDMI_4 (246)	"TVInputHDMI4"	"TVInputHDMI4"	"TVInputHDMI4"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_INPUT_COMPOSITE_1 (247)	"TVInputComposite1"	"TVInputComposite1"	"TVInputComposite1"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_INPUT_COMPOSITE_2 (248)	"TVInputComposite2"	"TVInputComposite2"	"TVInputComposite2"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_INPUT_COMPONENT_1 (249)	"TVInputComponent1"	"TVInputComponent1"	"TVInputComponent1"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_INPUT_COMPONENT_2 (250)	"TVInputComponent2"	"TVInputComponent2"	"TVInputComponent2"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_INPUT_VGA_1 (251)	"TVInputVGA1"	"TVInputVGA1"	"TVInputVGA1"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_AUDIO_DESCRIPTION (252)	"TVAudioDescription"	"TVAudioDescription"	"TVAudioDescription"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_AUDIO_DESCRIPTION_MIX_UP (253)	"TVAudioDescriptionMixUp"	"TVAudioDescriptionMixUp"	"TVAudioDescriptionMixUp"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_AUDIO_DESCRIPTION_MIX_DOWN (254)	"TVAudioDescriptionMixDown"	"TVAudioDescriptionMixDown"	"TVAudioDescriptionMixDown"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)



virtual keycode	Gecko	Chromium	Spec	Notes
AKEYCODE_TV_ZOOM_MODE (255)	"ZoomToggle"	"ZoomToggle"	"ZoomToggle"	Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_CONTENTS_MENU (256)	"TVContentsMenu"	"TVContentsMenu"	"TVContentsMenu"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_TV_MEDIA_CONTEXT_MENU (257)	"Unidentified"	"Unidentified"		
AKEYCODE_TV_TIMER_PROGRAMMING (258)	"TVTimer"	"TVTimer"	"TVTimer"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_HELP (259)	"Help"	"Help"	"Help"	Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_NAVIGATE_PREVIOUS (260)	"NavigatePrevious"	"NavigatePrevious"	"NavigatePrevious"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_NAVIGATE_NEXT (261)	"NavigateNext"	"NavigateNext"	"NavigateNext"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_NAVIGATE_IN (262)	"NavigateIn"	"NavigateIn"	"NavigateIn"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_NAVIGATE_OUT (263)	"NavigateOut"	"NavigateOut"	"NavigateOut"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_STEM_PRIMARY (264)	"Unidentified"	"Unidentified"		
AKEYCODE_STEM_1 (265)	"Unidentified"	"Unidentified"		
AKEYCODE_STEM_2 (266)	"Unidentified"	"Unidentified"		
AKEYCODE_STEM_2 (267)	"Unidentified"	"Unidentified"		
AKEYCODE_DPAD_UP_LEFT (268)	"Unidentified"	"Unidentified"		
AKEYCODE_DPAD_DOWN_LEFT (269)	"Unidentified"	"Unidentified"		
AKEYCODE_DPAD_UP_RIGHT (270)	"Unidentified"	"Unidentified"		
AKEYCODE_DPAD_DOWN_RIGHT (271)	"Unidentified"	"Unidentified"		
AKEYCODE_MEDIA_SKIP_FORWARD (272)	"MediaSkipForward"	"MediaSkipForward"	"MediaSkipForward"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_MEDIA_SKIP_BACKWARD (273)	"MediaSkipBackward"	"MediaSkipBackward"	"MediaSkipBackward"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_MEDIA_STEP_FORWARD (274)	"MediaStepForward"	"MediaStepForward"	"MediaStepForward"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_MEDIA_STEP_BACKWARD (275)	"MediaStepBackward"	"MediaStepBackward"	"MediaStepBackward"	Chromium fixed in crrev.com/2501083002, Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_SOFT_SLEEP (276)	"Unidentified"	"Unidentified"		
AKEYCODE_CUT (277)	"Cut"	"Cut"		Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_COPY (278)	"Copy"	"Copy"		Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_PASTE (279)	"Paste"	"Paste"		Gecko fixed in bugzil.la/1274503 (2)
AKEYCODE_SYSTEM_NAVIGATION_UP (280)	"Unidentified"	"Unidentified"		
AKEYCODE_SYSTEM_NAVIGATION_DOWN (281)	"Unidentified"	"Unidentified"		
AKEYCODE_SYSTEM_NAVIGATION_LEFT (282)	"Unidentified"	"Unidentified"		
AKEYCODE_SYSTEM_NAVIGATION_RIGHT (283)	"Unidentified"	"Unidentified"		