

Block (Property in Qube)

Fixflo Block (Block within the API Field)	QubePM Property Field
ExternalBlockRef	Reference
Name	Desc
AddressLine1	Line 1 = AddressLine1 Line 2 = AddressLine2 Line 3 = Town Line4 = County
AddressLine2	
Town	
PostCode	Postcode

Unit (Unit in Qube)

Fixflo Unit (Property within the API Field)	QubePM Property Field
ExternalPropertyRef	Unit Reference
AddressLine1	Unit Desc + Line 1 = AddressLine1 Line 2 = AddressLine2 Line 3 = Town Line4 = County
AddressLine2	
Town	
PostCode	Postcode

Landlord (Owner + address in Qube)

Fixflo Landlord Field	Qube PM Field (Owner Address)
ExternalLandlordRef	Owner reference
DisplayName	Name
CompanyName	Company
AddressLine1	Line 1 = AddressLine1 Line 2 = AddressLine2 Line 3 = Town Line4 = County
AddressLine2	
Town	
PostCode	Postcode
ContactNumber	Telephone[1]

EmailAddress	Email[1]
--------------	----------

Leaseholder (Tenant in Qube)

Fixflo Leaseholder (Tenant within the API) Field	Qube PM Field (Owner Address)
ExternalRef	Tenant reference (Alt address record number is appended for uniqueness when an alt address)
CompanyName	Name
CompanyName	Company
AddressLine1	Line 1 = AddressLine1 Line 2 = AddressLine2 Line 3 = Town Line4 = County
AddressLine2	
Town	
PostCode	Postcode
ContactNumber	Telephone[1]
ContactNumberAlt	Telephone[2]
EmailAddress	Email[1]

Contractor (Supplier in Qube)

Fixflo Contractor Field	QubePM Supplier Field
ExternalContractorRef	Reference
AddressLine1	
AddressLine2	
Town	
PostCode	Postcode
CompanyName	Name
EmailAddress	Email address specified by the supplier's 'Purchase order email setting' (found on the correspondence tab of the supplier in QubePM 2018+ or via a configuration setting pre-2018)

EmailCC	Email address is added here, instead of 'EmailAddress', if the email is already used by another contractor on Fixflo, in which case the 'EmailAddress' field is cleared
Tel1	Telephone[1]
Tel2	Telephone[2]