

Subnet Description	Public Network Address	Number of Host created	Subnet Mask	1st Public Usable Host Address	last Public Usable Host Address	Broadcast
Headquarters (CBR)	128.0.0.0	1022	255.255.252.0	128.0.0.1	128.0.3.254	128.0.3.255
Branch Office (SYD)	128.0.4.0	510	255.255.254.0	128.0.4.1	128.0.5.254	128.0.5.255
Branch Office (MEL)	128.0.6.0	510	255.255.254.0	128.0.6.1	128.0.7.254	128.0.7.255
Branch Office (LDN)	128.0.8.0	510	255.255.254.0	128.0.8.1	128.0.9.254	128.0.9.255
Branch Office (NY)	128.0.10.0	510	255.255.254.0	128.0.10.1	128.0.11.254	128.0.11.255
Admin (CBR)	128.0.12.0	126	255.255.255.128	128.0.12.1	128.0.12.126	128.0.12.127
Admin (SYD)	128.0.12.128	126	255.255.255.128	128.0.12.129	128.0.12.254	128.0.12.255
Admin (MELB)	128.0.13.0	126	255.255.255.128	128.0.13.1	128.0.13.126	128.0.13.127
Admin (LDN)	128.0.13.128	126	255.255.255.128	128.0.13.129	128.0.13.254	128.0.13.255
Admin (NY)	128.0.14.0	126	255.255.255.128	128.0.14.1	128.0.14.126	128.0.14.127
Reception (AU)	128.0.14.128	62	255.255.255.192	128.0.14.129	128.0.14.190	128.0.14.191
Reception (SYD)	128.0.14.192	62	255.255.255.192	128.0.14.193	128.0.14.254	128.0.14.255
Reception (MELB)	128.0.15.0	62	255.255.255.192	128.0.15.1	128.0.15.62	128.0.15.63
Reception (LDN)	128.0.15.64	62	255.255.255.192	128.0.15.65	128.0.15.126	128.0.15.127
Reception (NY)	128.0.15.128	62	255.255.255.192	128.0.15.129	128.0.15.190	128.0.15.191
DMZ (AU)	128.0.15.192	62	255.255.255.192	128.0.15.193	128.0.15.254	128.0.15.255
DMZ (LDN)	128.0.16.0	62	255.255.255.192	128.0.16.1	128.0.16.62	128.0.16.63
DMZ (NY)	128.0.16.64	62	255.255.255.192	128.0.16.65	128.0.16.126	128.0.16.127