

Guide to playing Journey to the Centre of Hawkthorne with Wiimote using Windows

This guide might seem quite long, but I'm just being thorough. It's actually very easy to connect your Wiimote and can be done in less than 15 minutes.

ENSURE YOUR COMPUTER HAS BLUETOOTH

- If it doesn't, you'll need [a bluetooth adapter](#)

ADD WIIMOTE AS A BLUETOOTH DEVICE

- Go to the bluetooth devices section of the control panel – if you're using a bluetooth adapter you may have to run it through the program you installed in step 1
- Click “add device”
- Hold down 1 & 2 on your Wiimote. Windows should recognise the device as “NINTENDO-RVT-CNT-01”. It will then install drivers (check the lights on your remote are still flashing)
- The first blue light on your Wiimote should now be lit

DOWNLOAD GLOVEPIE

- Download [glovepie](#) and extract the zip file into a folder

DOWNLOAD FILES FOR CONTROLLING COMPUTER WITH WII

- Download the following files, [WiiVertical.pie](#) and [WiiHorizontal.pie](#)
- Save them in the “WiimoteScripts” subfolder of glovepie

PLAYING THE GAME USING THE REMOTE

- Run glovepie.exe
- Open “WiiVertical” or “WiiHorizontal” depending on how you hold the controller
- Click “Run”
- Play Hawkthorne

Here is the default list of the controls.

Action	Keyboard	Wii (vertical)	Wii (horizontal)
Up, look up, pick up item	up arrow	up	right
Down, crouch	down arrow	down	left
Left	left arrow	left	down
Right	right arrow	right	up
Action, select	Z	A	1
Jump	X	B	2
Inventory	Enter	1	A

CUSTOM CONTROLS

It is very simple to alter this to your own preferences. Each alternative to the keyboard key from column 2 is written in 6 lines of code which look like this:

```
// Left
if wiimote.Left then
Key.left = true
wait 150 ms
Key.left = false
endif
```

Green	The action (i.e. column 1) this code affects
Blue	The associated key on the wii remote
Yellow	The associated key on the keyboard
Pink	Length of time key is active

You can alter the stuff in blue and pink - just open the file in glovepie.

If you want to change which button you use on the remote, find the relevant green action and change the blue one. Possible values are (Left, Right, Up, Down, A, B, 1, 2, Plus, Minus, Home) .

Other issues – alter the pink value.

Scrolling up&down / left & right too quickly through menus	Increase up & down or left & right wait
Can't access cheat menu	Try pressing the buttons more slowly or increase left & right wait
Can't jump high enough	Increase jump wait
Scrolling through costume select too quickly	Increase jump wait

The pink values work for my computer but if you have any other issues, work out which button is the problem. Remember you can still use your keyboard so trial and error will tell you which key is being the pain. Then try increasing / decreasing wait for the action associated with that key. If you don't have a clue – go extremes (e.g. 10ms or 1000ms) to see what happens.