

```
Osmo-trx-uhd
log stderr
logging filter all 1
logging color 1
logging print category 1
logging timestamp 1
logging print file basename
logging level set-all notice
!
line vty
no login
!
trx
bind-ip 127.0.0.9
remote-ip 127.0.0.9
base-port 5700
egprs enable
swap-channels enable
tx-sps 4
rx-sps 4
chan 0
rx-path RX2
tx-path TX/RX
```

Log

```
sudo osmo-trx-uhd -C /etc/osmocom/osmo-trx-uhd.cfg
[sudo] password for tahmid:
Sun May 21 02:04:06 2023 DLGLOBAL <0008> telnet_interface.c:88 Available via telnet
127.0.0.1 4237
Sun May 21 02:04:06 2023 DLCTRL <000f> control_if.c:1014 CTRL at 127.0.0.1 4236
[INFO] [UHD] linux; GNU C++ version 11.2.0; Boost_107400; UHD_4.1.0.5-3
Sun May 21 02:04:24 2023 DMAIN <0000> osmo-trx.cpp:607 -- Transceiver active with 1
channel(s)
Sun May 21 02:04:24 2023 DLSTATS <0011> stats.c:169 Stats timer expire_count=4: We
missed 3 timers
Sun May 21 02:04:24 2023 DLGLOBAL <0008> rate_ctr.c:350 Stats timer expire_count=17: We
missed 16 timers
Sun May 21 02:04:25 2023 DTRXCTRL <0002> Transceiver.cpp:976 Changing TSC from 0 to 7
Sun May 21 02:04:25 2023 DTRXCTRL <0002> Transceiver.cpp:1003 [chan=0] switching to
TRXD version 1
Sun May 21 02:04:25 2023 DMAIN <0000> Transceiver.cpp:284 Starting the transceiver
Sun May 21 02:04:25 2023 DMAIN <0000> Transceiver.cpp:280 Transceiver already running
LLSun May 21 02:04:25 2023 DTRXCLK <0001> Transceiver.cpp:1142 Sending CLOCK
indications
```

UUL